

# HI-LO, GAME OF USER INSTRUCTIONS

1. Reload card. (ON-RUN).
2. Key in seed, press STO 6.
3. Press A.
4. Press R/S.
5. Key in guess, press R/S. Display will be in form of 0.NNN, or NNN.000.
6. Repeat step #5 until you guess the number.
7. When you have guessed the number, the number of guesses is flashed.
8. For a new number, go to step #5.

Seed = .123456

#  
63  
245  
646  
276  
404  
679

001 f LBL A	3125 11	033 5	05
002 f FIX	31 23	034 h Y <sup>X</sup>	35 63
003 DSP 0	23 00	035 g FRAC	32 83
004 CLX	44	036 STO 6	33 06
005 f LBL B	31 25 12	037 3	03
006 R/S	84	038 g 10 <sup>X</sup>	32 53
007 ENTER	41	039 x	71
008 $\sum +$	21	040 f INT	31 83
009 RCL 7	34 07	041 STO 7	33 07
010 h X $\leftrightarrow$ Y	35 52	042 GTO A	22 11
011 g X=Y?	32 51	043 f LBL 3	31 25 03
012 GTO 2	22 02	044 STO 8	33 08
013 g X>Y?	32 81	045 f GSB 5	31 22 05
014 GTO 3	22 03	046 GTO A	22 11
015 g X $\leq$ Y?	32 71	047 f LBL 4	31 25 04
016 GTO 4	22 04	048 STO 9	33 09
017 GTO 1	22 01	049 f GSB 5	31 22 05
018 f LBL 2	31 25 02	050 GTO A	22 11
019 9	09	051 f LBL 5	31 25 05
020 g 10 <sup>X</sup>	32 53	052 RCL 8	34 08
021 h RCL I	35 34	053 f FIX	31 23
022 f P $\leftrightarrow$ S	31 42	054 DSP 3	23 03
023 RCL 9	34 09	055 REX	43
024 h PAUSE	35 72	056 3	03
025 f CL REG	31 43	057 $\div$	81
026 f P $\leftrightarrow$ S	31 42	058 RCL 9	34 09
027 0	00	059 h ABS	35 64
028 STO 8	33 08	060 +	61
029 STO 9	33 09	061 h PAUSE	35 72
030 h $\pi$	35 73	062 h PAUSE	35 72
031 RCL 6	34 06	063 h RTN	35 22
032 +	61	064 GTO A	22 11