

LOGIC GAME II

USER INSTRUCTIONS

1. Reload card. (ON-RUN).
2. Key in decimal seed, press A.
3. Key in guess, press B.
4. Repeat step #3 until number is guessed. When number is guessed, the number of guesses needed is displayed.
5. For a new game, press C, then go to Step #3.

001 f LBL A	31 25 11	032 h H \leftrightarrow Y	35 52
002 9	09	033 g X \neq Y?	32 61
003 9	09	034 GTO 9	22 09
004 8	08	035 RCL 7	34 07
005 STO 5	33 05	036 h RTN	35 22
006 h R \downarrow	35 53	037 f LBL 9	31 25 09
007 STO 4	33 04	038 g X > Y?	32 81
008 f LBL 1	31 25 01	039 GTO 9	22 09
009 2	02	040 CHS	42
010 9	09	041 h RTN	35 22
011 STO 4	34 04	042 f LBL 9	31 25 09
012 x	71	043 g X \leq Y?	32 71
013 g FRAC	32 83	044 GTO 9	22 09
014 RCL 5	34 05	045 f LBL 8	31 25 08
015 x	71	046 h RTN	35 22
016 1	01	047 f LBL 9	31 25 09
017	61	048 f LBL C	31 25 13
018 f INT	31 83	049 h LST x	35 82
019 1	01	050 g FRAC	32 83
020 0	00	051 STO 4	33 04
021 0	00	052 GTO 1	22 01
022 g X > Y?	32 81	053 f LBL D	31 25 14
023 GTO 9	22 09	054 h R \downarrow	35 53
024 GTO 0	22 00	055 STO 6	33 06
025 f LBL 9	31 25 09	056 CLX	44
026 GTO C	22 13	057 ENTER	41
027 f LBL B	31 25 12	058 ENTER	41
028 1	01	059 ENTER	41
029 STO+7	33 61 07	060 STO 7	33 07
030 h R \downarrow	35 53	061 h RTN	35 22
031 RCL 6	34 06		

SEED .97351

284
239
981
463
618
256
889
587
138
158