

# 67 TWIX - AN OLD PPC GAME

## 67 TWIX

|     |    |    |    |          |
|-----|----|----|----|----------|
| 001 | 31 | 25 | 13 | LBL C    |
| 002 |    | 31 | 43 | CL REG   |
| 003 |    |    | 09 | 9        |
| 004 |    | 35 | 62 | 1/x      |
| 005 |    |    | 43 | EEX      |
| 006 |    |    | 01 | 1        |
| 007 |    |    | 00 | 0        |
| 008 |    |    | 71 | X        |
| 009 |    |    | 01 | 1        |
| 010 |    |    | 51 | -        |
| 011 |    |    | 01 | 1        |
| 012 |    |    | 02 | 2        |
| 013 |    |    | 03 | 3        |
| 014 |    |    | 04 | 4        |
| 015 |    |    | 05 | 5        |
| 016 |    |    | 06 | 6        |
| 017 |    |    | 07 | 7        |
| 018 |    |    | 08 | 8        |
| 019 |    |    | 09 | 9        |
| 020 |    | 33 | 00 | STO 0    |
| 021 |    |    | 51 | -        |
| 022 |    | 35 | 22 | RTN      |
| 023 | 31 | 25 | 11 | LBL A    |
| 024 |    | 31 | 34 | ISZ      |
| 025 |    |    | 43 | EEX      |
| 026 |    |    | 07 | 7        |
| 027 |    |    | 81 | ./.      |
| 028 |    |    | 41 | ENTER    |
| 029 |    | 31 | 83 | INT      |
| 030 |    |    | 01 | 1        |
| 031 |    |    | 00 | 0        |
| 032 |    |    | 81 | ./.      |
| 033 |    | 33 | 02 | STO 2    |
| 034 |    | 32 | 83 | FRAC     |
| 035 |    |    | 43 | EEX      |
| 036 |    |    | 02 | 2        |
| 037 |    |    | 71 | X        |
| 038 |    | 34 | 02 | RCL 2    |
| 039 |    | 31 | 83 | INT      |
| 040 |    |    | 61 | +        |
| 041 |    | 35 | 52 | X EXCH Y |
| 042 |    | 32 | 83 | FRAC     |
| 043 |    |    | 61 | +        |
| 044 |    |    | 43 | EEX      |
| 045 |    |    | 07 | 7        |
| 046 |    |    | 71 | X        |
| 047 |    | 22 | 00 | GTO 0    |
| 048 | 31 | 25 | 12 | LBL B    |
| 049 |    | 31 | 34 | ISZ      |
| 050 |    |    | 43 | EEX      |
| 051 |    |    | 08 | 8        |
| 052 |    |    | 81 | ./.      |
| 053 |    |    | 41 | ENTER    |
| 054 |    | 31 | 83 | INT      |

|     |    |    |       |
|-----|----|----|-------|
| 055 |    | 43 | EEX   |
| 056 |    | 09 | 9     |
| 057 |    | 81 | ./.   |
| 058 |    | 61 | +     |
| 059 |    | 32 | 83    |
| 060 |    | 43 | EEX   |
| 061 |    | 09 | 9     |
| 062 |    | 71 | X     |
| 063 |    | 22 | 00    |
| 064 | 31 | 25 | 14    |
| 065 |    | 31 | 34    |
| 066 |    | 01 | 1     |
| 067 |    | 00 | 0     |
| 068 |    | 81 | ./.   |
| 069 |    | 41 | ENTER |
| 070 |    | 32 | 83    |
| 071 |    | 43 | EEX   |
| 072 |    | 09 | 9     |
| 073 |    | 71 | X     |
| 074 |    | 61 | +     |
| 075 |    | 31 | 83    |
| 076 |    | 22 | 00    |
| 077 | 31 | 25 | 15    |
| 078 |    | 31 | 34    |
| 079 |    | 43 | EEX   |
| 080 |    | 02 | 2     |
| 081 |    | 81 | ./.   |
| 082 |    | 41 | ENTER |
| 083 |    | 32 | 83    |
| 084 |    | 01 | 1     |
| 085 |    | 00 | 0     |
| 086 |    | 71 | X     |
| 087 |    | 33 | 02    |
| 088 |    | 32 | 83    |
| 089 |    | 43 | EEX   |
| 090 |    | 02 | 2     |
| 091 |    | 71 | X     |
| 092 |    | 34 | 02    |
| 093 |    | 31 | 83    |
| 094 |    | 61 | +     |
| 095 |    | 35 | 52    |
| 096 |    | 31 | 83    |
| 097 |    | 43 | EEX   |
| 098 |    | 02 | 2     |
| 099 |    | 71 | X     |
| 100 |    | 61 | +     |
| 101 | 31 | 25 | 00    |
| 102 |    | 34 | 00    |
| 103 |    | 35 | 52    |
| 104 |    | 32 | 61    |
| 105 |    | 35 | 22    |
| 106 |    | 31 | 84    |
| 107 |    | 35 | 34    |
| 108 |    | 84 | R/S   |

Set display mode to FIX, DSP 0 before recording.  
James Garon (2042)

## TIPS

R/S

**QUICK NOTE ON MAG CARD HOLDERS-** There are at least two types of card holders available from Hewlett-Packard. Every 67/97 owner is familiar with the pink plastic type which came with the Standard Pac. This type is also available with the other Application Pacs and the Blank Cards, and are less likely to present any problems for the storage of Mag Cards with rub-on lettering. The other type is a grayish-tan color and are what you receive when you order the Mag Card Holders alone. Fixatives, rub-on lettering, and even "SHARPIE" pen lettering stick or transfer to the Clear Plastic of this grayish-tan type of card holder and are suitable only for the storage of program cards produced by Hewlett Packard.

M. WALLON (1431)

R/S