

BINGO, NUMBER GENERATOR

USER INSTRUCTIONS

1. Reload card. (ON-RUN).
2. Key in seed, press B.
3. Press R/S to generate remaining numbers.
4. Continue pressing R/S until game is finished.
5. For a new game, press B.
6. Go to step #3.

Seed = .123456

Draw

1. 25	26. 40	61. 4
2. 29	27. 53	62. 35
3. 66	28. 23	63. 71
4. 12	29. 39	64. 3
5. 48	30. 55	65. 38
6. 51	31. 14	66. 70
7. 6	32. 44	67. 13
8. 37	33. 59	68. 34
9. 61	34. 22	69. 69
10. 17	35. 26	70. 8
11. 31	36. 52	71. 32
12. 64	37. 7	72. 68
13. 21	38. 47	73. 1
14. 36	39. 74	74. 30
15. 65	40. 20	75. 67
16. 15	41. 46	
17. 50	42. 73	
18. 60	43. 2	
19. 10	44. 45	
20. 49	45. 63	
21. 75	46. 16	
22. 24	47. 33	
23. 27	48. 62	
24. 58	49. 9	
25. 19	50. 28	
	51. 57	
	52. 18	
	53. 43	
	54. 56	
	55. 5	
	56. 42	
	57. 54	
	58. 11	
	59. 41	
	60. 72	

001	f LBL B	31	25	12
002	STO 0	33	00	
003	3	03		
004	3	03		
005	5	05		
006	5	05		
007	4	04		
008	4	04		
009	3	03		
010	1	01		
011	.	83		
012	5	05		
013	STO 1	33	01	
014	STO 2	33	02	
015	STO 3	33	03	
016	5	05		
017	0	00		
018	STO 4	33	04	
019	0	00		
020	.	83		
021	4	04		
022	9	09		
023	9	09		
024	9	09		
025	9	09		
026	9	09		
027	9	09		
028	9	09		
029	9	09		
030	STO 6	33	06	
031	GTO A	22	11	
032	f LBL A	31	25	11
033	RCL 1	34	01	
034	RCL 2	34	02	
035	STO 1	33	01	
036	RCL 3	34	03	
037	STO 2	33	02	
038	h R ↓	35	53	
039	h R ↓	35	53	
040	STO 3	33	03	
041	RCL 0	34	00	
042	g TAN ⁻¹	32	64	
043	g FRAC	32	83	
044	STO 0	33	00	
045	2	02		

046	5	05		
047	STO+4	33	61	04
048	x	71		
049	f LBL 4	31	25	04
050	f INT	31	83	
051	f X≠0?	31	61	
052	GTO 2	22	02	
053	2	02		
054	5	05		
055	f LBL 2	31	25	02
056	STO 5	33	05	
057	RCL 1	34	01	
058	RCL 6	34	06	
059	RCL 5	34	05	
060	CHS	42		
061	h Y ^x	35	63	
062	f INT	31	83	
063	STO 7	33	07	
064	÷	81		
065	g FRAC	32	83	
066	RCL 6	34	06	
067	g X≤Y?	32	51	
068	GTO 5	22	05	
069	g X=Y?	32	71	
070	GTO 3	22	03	
071	f LBL 5	31	25	05
072	STO-5	33	51	05
073	RCL 5	34	05	
074	GTO 4	22	04	
075	f LBL 3	31	25	03
076	RCL 7	34	07	
077	2	02		
078	÷	81		
079	STO-1	33	51	01
080	7	07		
081	5	05		
082	RCL 4	34	04	
083	g X=Y?	32	51	
084	0	00		
085	STO 4	33	04	
086	RCL 5	34	05	
087	+	61		
088	R/S	84		
089	GTO A	22	11	