

# CALCULATOR EVALUATOR

## User instructions

1. To run, press A,B,C,D, or E.

001 f LBL A	31 25 11	039 GTO (1)	22 24	
002 f GSB 6	31 22 06	040 f LBL D	31 25 14	
003 6	06	041 f GSB 0	31 22 00	
004 RCL 0	34 00	042 RCL 0	34 00	
005 f -x-	31 84	043 STO 2	33 02	
006 CLX	44	044 STO 4	33 04	
007 RCL 1	34 01	045 STO 6	33 06	
008 f -x-	31 84	046 STO 8	33 08	
009 CLX	44	047 STO A	33 11	
010 GTO (1)	22 24	048 STO C	33 13	
011 f LBL C	31 25 13	049 RCL 1	34 01	
012 f GSB 6	31 22 06	050 STO 3	33 03	
013 RCL 0	34 00	051 STO 5	33 05	
014 h PAUSE	35 72	052 STO 7	33 07	
015 CLX	44	053 STO 9	33 09	
016 RCL 1	34 01	054 STO B	33 12	
017 h PAUSE	35 72	055 STO D	33 14	
018 CLX	44	056 h REG	35 74	
019 GTO (1)	22 24	057 GTO (i)	22 24	
020 f LBL 0	31 25 00	058 f LBL E	31 25 15	
021 ENTER	41	059 h CF 1	35 61 01	
022 1	01	060 f LBL 1	31 25 01	
023 CHS	42	061 h F? 1	35 71 01	
024 h STO I	35 33	062 GTO 2	22 02	
025 h RTN	35 22	063 h SF 1	35 51 01	
026 f LBL 6	31 25 06	064 RCL 0	34 00	
027 ENTER	41	065 GTO 3	22 03	
028 6	06	066 f LBL 2	31 25 02	
029 CHS	42	067 h CF 1	35 61 01	
030 h STO I	35 33	068 RCL 1	34 01	
031 h RTN	35 22	069 f LBL 3	31 25 03	
032 f LBL B	31 25 12	070 RCL E	34 15	
033 f GSB 0	31 22 00	071 GTO .AD	31 25 24	f LBL i
034 RCL 0	34 00	072 ↓	↓	↓
035 RCL 1	34 01	↓	↓	↓
036 RCL 0	34 00	111 GTO .AD	31 25 24	f LBL i
037 RCL 1	34 01	112 GTO 1	22 01	
038 g STK	32 84			

## Registers

0. 67 is cool  
 1. sr 52 boo  
 E. -4.000000000 22