

HP COMMERCIAL

User instructions

1. Reload program card, both sides.
2. Reload data card, both sides.
3. Press A to start.

001 f LBL A	31 25 11	041 RCL 0	34 00	
002 RCL 9	34 09	042 f GSB 0	31 22 00	
003 f GSB 0	31 22 00	043 RCL A	34 11	
004 RCL 8	34 08	044 f GSB 0	31 22 00	
005 f GSB 0	31 22 00	045 RCL B	34 12	
006 RCL 7	34 07	046 f GSB 0	31 22 00	
007 f GSB 0	31 22 00	047 RCL C	34 13	
008 RCL 6	34 06	048 f GSB 0	31 22 00	
009 f GSB 0	31 22 00	049 RCL D	34 14	
010 RCL 5	34 05	050 f GSB 0	31 22 00	
011 f GSB 0	31 22 00	051 RCL E	34 15	
012 RCL 4	34 04	052 f GSB 0	31 22 00	
013 f GSB 0	31 22 00	053 f P ↔ S	31 42	
014 RCL 3	34 03	054 RCL 0	34 00	
015 f GSB 0	31 22 00	055 f GSB 1	31 22 01	
016 RCL 2	34 02	056 RCL E	34 15	
017 f GSB 0	31 22 00	057 f GSB 1	31 22 01	
018 RCL 1	34 01	058 h SPACE	35 84	
019 f GSB 0	31 22 00	059 GTO A	22 11	
020 RCL 0	34 00	060 f LBL 0	31 25 00	
021 f GSB 0	31 22 00	061 f RND	31 24	
022 f P ↔ S	31 42	062 h RCL I	35 34	
023 RCL 9	34 09	063 GTO .AD	31 25 24	f LBL 1
024 f GSB 0	31 22 00	↓ ↓ ↓	↓	↓
025 RCL 8	34 08	091 GTO .AD	31 25 24	f LBL 1
026 f GSB 0	31 22 00	092 h RTN	35 22	
027 RCL 7	34 07	093 GTO .AD	31 25 24	f LBL 1
028 f GSB 0	31 22 00	↓ ↓ ↓	↓	↓
029 RCL 6	34 06	103 GTO .AD	31 25 24	f LBL 1
030 f GSB 0	31 22 00	104 h RTN	35 22	
031 RCL 5	34 05	105 f LBL 1	31 25 01	
032 f GSB 0	31 22 00	106 f RND	31 24	
033 RCL 4	34 04	107 h RCL I	35 34	
034 f GSB 0	31 22 00	108 GTO .AD	31 25 24	f LBL 1
035 RCL 3	34 03	↓ ↓ ↓	↓	↓
036 f GSB 0	31 22 00	187 GTO .AD	31 25 24	f LBL 1
037 RCL 2	34 02	188 h RTN	35 22	
038 f GSB 0	31 22 00	189 GTO .AD	31 25 24	f LBL 1
039 RCL 1	34 01	↓ ↓ ↓	↓	↓
040 f GSB 0	31 22 00	221 GTO .AD	31 25 24	f LBL 1

(OVER)

REGISTERS

PRIMARY

0. A 67 OR 97
1. A 67 OR 9
2. A 67 OR
3. A 67 OR
4. A 67 0
5. A 67
6. A 67
7. A 6
8. A
9. A
A. IS A GOOD
B. S A GOOD D
C. A GOOD DE
D. A GOOD DEA
E. GOOD DEAL
I. 4.000000000 22

SECONDARY

0. IS A GOOD
1. 7 IS A GOO
2. 97 IS A GO
3. 97 IS A G
4. R 97 IS A
5. OR 97 IS A
6. OR 97 IS
7. 7 OR 97 IS
8. 67 OR 97 I
9. 67 OR 97