

SEASONS GREETINGS, 1977 P-2

User instructions, my program

1. Reload card, side 1&2
2. Continuous loop, delete R/S at step 045 & 018, press A slow, E fast.
3. One time and stop, press A for slow, press E for fast.

001 f LBL A	31 25 11	024 RCL 1	34 01
002 f FIX	31 23	025 h PAUSE	35 72
003 RCL 0	34 00	026 RCL 2	34 02
004 RCL 1	34 01	027 h PAUSE	35 72
005 RCL 2	34 02	028 RCL 3	34 03
006 RCL 3	34 03	029 h PAUSE	35 72
007 g STK	32 84	030 RCL 0	34 00
008 RCL 0	34 00	031 h PAUSE	35 72
009 RCL 4	34 04	032 RCL 4	34 04
010 RCL 5	34 05	033 h PAUSE	35 72
011 RCL 6	34 06	034 RCL 5	34 05
012 g STK	32 84	035 h PAUSE	35 72
013 RCL 7	34 07	036 RCL 6	34 06
014 RCL 0	34 00	037 h PAUSE	35 72
015 RCL 8	34 08	038 RCL 7	34 07
016 RCL 0	34 00	039 h PAUSE	35 72
017 g STK	32 84	040 RCL 0	34 00
018 R/S	84	041 h PAUSE	35 72
019 GTO A	22 11	042 RCL 8	34 08
020 f LBL E	31 25 15	043 h PAUSE	35 72
021 f FIX	31 23	044 RCL 0	34 00
022 RCL 0	34 00	045 R/S	84
023 h PAUSE	35 72	046 GTO E	22 15

Registers, same for both programs.

0. 0 0 0 0 0
1. BE DEC 25
2. A GLAD DAY
3. ALL DAY
4. BE 1977
5. A GOOD
6. YEAR
7. ALL YEAR
8. GOD BLESS

User instructions

1. Reload card, side 1&2.
2. To run, press A,B,C,D, or E.

001 f LBL A	31 25 11	012 RCL 4	34 04
002 f LBL B	31 25 12	013 RCL 5	34 05
003 f LBL C	31 25 13	014 RCL 6	34 06
004 f LBL D	31 25 14	015 g STK	32 84
005 f LBL E	31 25 15	016 RCL 7	34 07
006 RCL 0	34 00	017 RCL 0	34 00
007 RCL 1	34 01	018 RCL 8	34 08
008 RCL 2	34 02	019 RCL 0	34 00
009 RCL 3	34 03	020 g STK	32 84
010 g STK	32 84	021 CLX	44
011 RCL 0	34 00	022 GTO 1	22 24